

TECHNICAL UPDATE SERIES E

MAY 13TH 2020



SOFTWARE VERSION 3.1 -NEW RELEASE

The new Zipwake Series E Software Version 3.1 (E-R2945) incorporates the following improvements together with smaller enhancements.

- Function added to manual roll control that locks at equal port/starboard position when adjusting roll manually. The function simplifies manual adjustment back to neutral roll control. If the roll wheel is turned fast, the lock-function does not activate. The duration of the lock-function is 1 sec.
- Adjusted servo unit break limit during Interceptor Check to accurately execute the complete test sequence.
- Minor software improvements.

SYSTEM UPGRADE

Download the software upgrade file from www.zipwake.com and copy it to the root of a high quality USB memory stick. Then refer to the Operator's Manual Section 17 and follow the remaining steps.



Follow us

